



[Knowledgebase](#) > [TRACE32 PowerView](#) > [After updating TRACE32, I get larger fonts and dialogs when using Windows Scaling > 100%](#)

## After updating TRACE32, I get larger fonts and dialogs when using Windows Scaling > 100%

2023-10-25 - [Comments \(0\)](#) - [TRACE32 PowerView](#)

This is caused by the High-DPI support in TRACE32 PowerView which has been introduced in rev. 147211 (May 2022). Users with High-DPI monitors and a scaling setting >100% will experience increased font sizes in PowerView. If you prefer the original small font size, add the commands "**SETUP.GUI.FontSize 14.**" and "**SETUP.GUI.DialogFontSize 16.**" to the User's Autostart script (menu: File > Automatic Scripts on Start > Edit User's Autostart Script)